


# Readme (ENG-US)



# Foreword

Hello, first of all thank you for downloading the interior display mod for the Citybus O405.

**Please read this readme with extreme accuracy**, otherwise the function cannot be guaranteed. Please make sure to make a **backup of the original files**.  
**We are not liable for software errors.**

A big thank you goes to **Oceanic for testing the modification** and to **Pedro for creating this addon**.

Known bugs:

- Missing illumination in the trailing unit (G)
- Interior display "sticks" to the lamp in the trailer (G)
- Interior display can not yet be change via repaint as of **05.09.2023**

## Note:

- This modification may not be uploaded again
- Uploading on other websites is only allowed with the reference to the download link from the webdisk and only by naming the original author

**\* Translated by DeepL**

# Step-by-Step-Installation

## Step 1:

Open your main OMSI directory and **at the same time the folder "OMSI 2" in this archive.**

## Step 2:

**Drag the "Vehicles" folder from this archive** into your main OMSI directory. Nothing should be replaced.

## Step 3:

Now go back to your previously opened main directory and open the Vehicles folder there. Then search for the folder "0405" and open it. Once there, open the Model folder. Please do not close the folder!

## Step 4:

Now make a backup copy of the following files:

- model\_o405.cfg
- model\_o405Gmain.cfg
- model\_o405Gtrail.cfg

## Step 5:

Now open the **model\_o405.cfg** and search with CTRL+F for "**Script textures**".

## Step 6:

Paste above the previously searched and below the last text texture the following:

```
30
[texturetexture_enh]
act_busstop
LCD-Innenanzeige
1512
100
0
255
220
20
1
1
```

Afterwards it should look like this (inserted section is marked yellow):

```
29
[texture]
timer_text
IBIS-2_5x7
102
46
0
0
0
0
30
[texture_enh]
act_busstop
LCD-Innenanzeige
1512
100
0
255
220
20
1
1
#####
Script-Texturen:
#####

0: Krüger-Speicher
[scripttexture]
128
64
```

After that, **please save, but keep the file open**, because we are not done here yet.

### **Step 7:**

Now open the file "**Eintraege\_0405\_Solo\_&\_0405G\_main.txt**" in the folder mentioned in step 3 (Vehicles\0405\Model) and select the complete contents of the document with CTRL+A after opening the text editor. Then press CTRL+C to copy it to the clipboard.

### **Step 8:**

Now go back to **model\_o405.cfg** and scroll to **the bottom of the file**.

### **Step 9:**

Press the Enter key once after the last character of the file, which moves the cursor down one line. Now paste the previously copied entries with CTRL+V. And finally save once.

### **Step 10:**

Now open the **model\_o405Gmain.cfg** and search with CTRL+F for "**Script textures**".

### **Step 11:**

Paste above the previously searched and below the last text texture the following:

```
30
[texturetexture_enh]
act_busstop
LCD-Innenanzeige
1512
100
0
255
220
20
1
1
```

Afterwards it should look like this (inserted section is marked yellow):

```
29
[texture]
timer_text
IBIS-2_5x7
102
46
0
0
0
0

30
[texture_enh]
act_busstop
LCD-Innenanzeige
1512
100
0
255
220
20
1
1

#####
Script-Texturen:
#####

0: Krüger-Speicher
[scripttexture]
128
64
```

After that, **please save, but keep the file open**, because we are not done here yet.

## **Step 12:**

Now open the file "**Eintraege\_0405\_Solo\_&\_0405G\_main.txt**" in the folder mentioned in step 3 (Vehicles\0405\Model) and select the complete contents

of the document with CTRL+A after opening the text editor. Then press CTRL+C to copy it to the clipboard.

### **Step 13:**

Now go back to **model\_o405Gmain.cfg** and scroll to the **bottom of the file**.

### **Step 14:**

Press the Enter key once after the last character of the file, which moves the cursor down one line. Now paste the previously copied entries with CTRL+V. And finally save once.

### **Step 15:**

Now we open the **model\_o405Gtrail.cfg** and search with CTRL+F for "[LOD]".

### **Step 16:**

Paste above the previously searched and below the last text texture the following:

```
6
[texturetexture_enh]
act_busstop
LCD-Innenanzeige
1512
100
0
255
220
20
1
1
```

Afterwards it should look like this (inserted section is marked yellow)

```
5
[texture]
Matrix_Terminus
Annax_Small
512
128
0
176
191
105
```

```
6
[texture_enh]
act_busstop
LCD-Innenanzeige
1512
100
0
255
220
20
1
1
```

```
#####
[LOD]
0.1
#####
```

After that, **please save, but keep the file open**, because we are not done here yet.

### **Step 17:**

Now open the file "**Eintraege\_0405G\_Trail\_KRUEGER.txt**" in the folder mentioned in step 3 (Vehicles\0405\Model) and select the complete contents of the document with CTRL+A after opening the text editor. Then press CTRL+C to copy it to the clipboard.

### **Step 18:**

Now go back to **model\_o405Gtrail.cfg** and scroll to the bottom of the file.

### **Step 19:**

Press the Enter key once after the last character of the file, which moves the cursor down one line. Now paste the previously copied entries with CTRL+V. Do not forget to save. Start OMSI and drive off.